

# Help:

delay(1000);

{

Shift register allocation and initialization::

myShiftRegister.auto\_update = false;

myShiftRegister.OnSingleAllRegisters(7);

myShiftRegister.OnSingleAllRegisters(12);

myShiftRegister.UpdateAllRegisters();

myShiftRegister.OffAllRegisters();

Shift595Arduino(int datapin, int clockpin, int latchpin, int nbregisters=1);

```
/*
Allocation function:
    - datapin: specifies the Arduino pin connected to the 595 data input
    - clockpin: specifies the Arduino pin connected to the 595 clock input
    - latchpin: specifies the Arduino pin connected to the 595 latch output
    - nbregisters: specifies the number of cascaded registers. Default is 1.
ex: Shift595Arduino myShiftRegister(2, 3, 4, 2);
*/
```

# boolean Setup();

```
/*
Setup function:
    Inits the Arduino pins.
    This function must be called in the setup()
    function of the Arduino progam.

ex: myShiftRegister.Setup();
*/
```

# Shift register actions::

# boolean OffRegister(int reg\_index);

```
/*
Turn Off ('0') values of a specifc register:
    - reg_index: specify a register index.

ex: myShiftRegister.OffRegister(1);
*/
```

## boolean OffAllRegisters();

```
/*
Turn Off ('0') values of all registers.
ex: myShiftRegister.OffAllRegisters();
*/
```

# boolean OnRegister(int reg\_index);

```
/*
turn On ('1') values of a specifc register:
    - reg_index: specify a register index.

ex: myShiftRegister.OnRegister(1);
*/

**boolean OnUpperHalfRegister(int reg_index);**

/*
Turn On ('1') values of the upper half of
a specifc register:
    - reg_index: specify a register index.

ex: myShiftRegister.OnUpperHalfRegister(1);
*/
```

## boolean OnLowerHalfRegister(int reg\_index);

```
/*
Turn On ('1') values of the lower half of
a specifc register:
   - reg_index: specify a register index.
ex: myShiftRegister.OnLowerHalfRegister(1);
```

```
*/
```

# boolean OffUpperHalfRegister(int reg\_index);

```
/*
Turn Off ('0') values of the upper half of
a specifc register:
   - reg_index: specify a register index.

ex: myShiftRegister.OffUpperHalfRegister(1);
*/
```

# boolean OffLowerHalfRegister(int reg\_index);

```
/*
Turn Off ('0') values of the lower half of
a specifc register:
   - reg_index: specify a register index.

ex: myShiftRegister.OffLowerHalfRegister(1);
*/
```

# boolean OnUpperHalfOnlyRegister(int reg\_index);

```
/*
Turn On ('1') values of the upper half of
a specifc register, turn Off other values:
    - reg_index: specify a register index.

ex: myShiftRegister.OnUpperHalfOnlyRegister(1);
*/
```

#### boolean OnLowerHalfOnlyRegister(int reg\_index);

```
/*
Turn On ('1') values of the lower half of
a specifc register, turn Off other values:
    - reg_index: specify a register index.

ex: myShiftRegister.OnLowerHalfOnlyRegister(1);
*/
```

# boolean OnAllRegisters();

```
/*
Turn On ('1') values of all registers.
ex: myShiftRegister.OnAllRegisters();
*/
```

# boolean OnSingleRegister(int position, int reg\_index);

```
ex: myShiftRegister.OnSingleRegister(3, 1);
*/
```

## boolean OnSingleAllRegisters(int position);

#### boolean OnSingleEachRegisters(int position);

# boolean OffSingleRegister(int position, int reg\_index);

#### boolean OffSingleAllRegisters(int position);

## boolean OffSingleEachRegisters(int position);

# boolean OnSingleOnlyRegister(int position, int reg\_index);

# boolean OnSingleOnlyAllRegisters(int position);

## boolean OnSingleOnlyEachRegisters(int position);

#### boolean OffSingleOnlyRegister(int position, int reg\_index);

## boolean OffSingleOnlyAllRegisters(int position);

#### boolean OffSingleEachRegisters(int position);

# boolean ShiftLeftRegister(boolean circular, int reg\_index);

```
/*
Shift to the left values of a specific register:

- circular: set whether the shift is circular.
- reg_index: specify a register index.

ex: // before: [1,0,0,1,1,0,0,0]
    myShiftRegister.ShiftLeftRegister(true, 1);
    // after: [0,0,1,1,0,0,0,1]

ex: // before: [1,0,0,1,1,0,0,0]
    myShiftRegister.ShiftLeftRegister(true, 1);
    // after: [0,0,1,1,0,0,0,0]
*/
```

#### boolean ShiftLeftAllRegisters(boolean circular);

```
/*
Shift to the left values for all registers:

- circular: set whether the shift is circular.

ex: // before: [1,0,0,1,1,0,0,0][1,1,0,0,0,0,0,0]
    myShiftRegister.ShiftLeftRegister(true);
    // after: [0,0,1,1,0,0,0,1][1,0,0,0,0,0,0,1]
*/
```

# boolean ShiftLeftEachRegisters(boolean circular);

```
/*
Shift to the left values for each registers:
    - circular: set whether the shift is circular.

ex: // before: [1,0,0,1,1,0,0,0][0,1,1,1,0,0,0,0]
    myShiftRegister.ShiftLeftRegister(true);
    // after: [0,0,1,1,0,0,0,1][1,1,1,0,0,0,0,0]
*/
```

## boolean ShiftRightRegister(boolean circular, int reg\_index);

```
/*
Shift to the right values of a specific register:

- circular: set whether the shift is circular.
- reg_index: specify a register index.

ex: // before: [1,0,0,1,1,0,0,1]
   myShiftRegister.ShiftRightRegister(true, 1);
   // after: [1,1,0,0,1,1,0,0]
```

```
ex: // before: [1,0,0,1,1,0,0,1]
    myShiftRegister.ShiftLeftRegister(true, 1);
    // after: [0,1,0,0,1,1,0,0]
*/
```

# boolean ShiftRightAllRegisters(boolean circular);

```
/*
Shift to the right values for all registers:
    - circular: set whether the shift is circular.

ex: // before: [1,0,0,1,1,0,0,0][1,1,0,0,0,0,0,1]
    myShiftRegister.ShiftLeftRegister(true);
    // after: [1,1,0,0,1,1,0,0][0,1,1,0,0,0,0,0]
*/
```

## boolean ShiftRightEachRegisters(boolean circular);

```
/*
Shift to the right values for each registers:

- circular: set whether the shift is circular.

ex: // before: [1,0,0,1,1,0,0,0][0,1,1,1,0,0,0,1]
    myShiftRegister.ShiftLeftRegister(true);
    // after: [0,1,0,0,1,1,0,0][1,0,1,1,1,0,0,0]
*/
```

## boolean NegateRegister(int reg\_index);

```
/*
Negate values of a specific register. On values are turned Off,
Off values are turned On:
    - reg_index: specify a register index.

ex: myShiftRegister.NegateRegister(1);
*/
```

#### boolean NegateAllRegisters();

```
/*
Negate values of all registers.
ex: myShiftRegister.NegateAllRegisters();
*/
```

# boolean UpdateAllRegisters();

```
/*
Update registers' state. Registers' output pins are updated
to their current values.
ex: myShiftRegister.Update();
*/
```

boolean UpdateRegister(int reg\_index); /\* Update register state of a sprcific register. Register output pins are updated to their current values.

```
ex: myShiftRegister.UpdateRegister(1);
```

# boolean BlinkRegister(int iter, int delay\_val, int reg\_index);

```
/*
Update Off then update to their current values the
output pins of a specific register.

- iter: number of blinks.
- delay_val: blink delay in milliseconds.

ex: myShiftRegister.BlinkRegister(5, 100, 1);
*/
```

## boolean BlinkAllRegisters(int iter, int delay\_val);

```
/*
Update Off then update to their current values the
output pins of the registers.

- iter: number of blinks.
- delay_val: blink delay in milliseconds.

ex: myShiftRegister.BlinkAllRegisters(5, 100);
*/
```

## boolean TestSequence();

```
/*
Run a test sequence for N cascaded registers with LEDs.

- Turn On all LEDs
- Blink LEDs 5 times @ 100ms
- Turn Off all LEDs
- Turn On 3 LEDs
- Shift the 3 LEDs positions to the left x times
- Turn On / Off groups of 8 LEDs in alternance
- Switch On / Off LED states in alternance

ex: myShiftRegister.TestSequence();
*/
```

# Shift register parameters::

## boolean verbose;

```
/*
Enable/Disable verbose output.
When enabled, each operation outpus a string with its name.
Default value is false.

ex: myShiftRegister.verbose = true
*/
```

# boolean auto\_update;

```
/*
Enable/Disable register state auto update.
When enabled, each action updates values of the registers' output pins,
```

```
then wait some amount of time defined by the update_delay value.
When disabled, registers' output pins remain unchanged until
an explicit call to Update().
Default value is true.

ex: myShiftRegister.auto_update = false;
   myShiftRegister.OffAllRegisters();
   myShiftRegister.OnSingleAllRegisters(7);
   myShiftRegister.OnSingleAllRegisters(12);
   myShiftRegister.Update();
   delay(1000);
*/
```

# int update\_delay;

```
/*
Set the amount of time, in milliseconds, an action auto update
is maintained before returning.
Default value is 0.

ex: myShiftRegister.update_delay = 250;
*/
```

Author: Arnaud D. LINA

© 2014 GitHub, Inc. Terms Privacy Security Contact

Status API Training Shop Blog About